

iOS IKEv2 client configuration

[Order now](#) | [Download](#) | [FAQ](#)

To connect to the VPN, follow these steps:

1. Open the provided link in your browser to get instructions and settings for your new VPN connection. You will see the following page in your browser window.

This is a one-time link with configuration options

WireGuard

[Download client Android](#)

[Download client iOS](#)

[Download client Windows](#)

[Download client macOS](#)

[Official clients WireGuard](#)



[Download config file](#)

```
[Interface]
Address = 10.0.111.16/24,2a11:ff00::111/120
DNS = 10.0.111.1,2a11:ff00::101,2a11:ff00::a
PrivateKey = G0mqdb66DPx6YdPZ/A4YDGIoAdAllgVAPsyhm1HQeb-

[Peer]
PersistentKeepalive = 25
Endpoint = dev.softkeel.com:51930
PublicKey = xbrvWbnN280sjH0yyzFw0Ey1UC-wvKQ8FG/cLoJh2w-
AllowedIPs = 0.0.0.0/0, ::/0
```

IKEv2

[Download Certificate CA](#)

Server: dev.softkeel.com

Username: user_3

Password: dupa

[Download Profile](#)

2. To proceed, you need to install the Certificate CA. Click the "Download Certificate CA" button and allow the download of the file.

IKEv2

Download Certificate CA

Server: dev.softkeel.com

Username: user_3

Password: dupa

Download Profile

Download client Android

Download client Debian/Ubuntu

Official clients strongSwan

doc.puq.info
www.puqcloud.com

3. Next, navigate to the following path: Settings -> General -> VPN & Device Management, and wait for the profile to download and appear in this window.

12:19



[< Back](#) VPN & Device Management

VPN

VPN

Not Connected >

[Sign In to Work or School Account...](#)


DOWNLOADED PROFILE




TEST_CN




4. Tap on the downloaded profile and, click the "Install" button.



5. Enter your password.



6. Read the warning and press the "Install" button



7. Press "Install" again to confirm.

12:19



Cancel

Warning

Install

UNMANAGED ROOT CERTIFICATE

Installing the certificate "TEST_CN" will add it to the list of trusted certificates on your iPhone. This certificate will not be trusted for websites until you enable it in Certificate Trust Settings.

UNVERIFIED PROFILE

The authenticity of "TEST_CN" cannot be verified.

Install

8. A window will appear, showing that the profile has been downloaded and verified.

12:19



Profile Installed

Done



TEST_CN

Signed by TEST_CN

Verified ✓

Contains Certificate

More Details



Next, you need to configure the VPN.

1. To do this, go to Settings -> General -> VPN & Device Management -> VPN and tap on "Add VPN Configuration..."

14:09

LTE

< Settings

VPN

VPNs can be set up to control the routing of certain network traffic. [About VPNs & Privacy...](#)

VPN CONFIGURATIONS

Status

Not Connected



To connect using "vpn.puq.pl", use the "OpenVPN" application.



vpn.puq.pl

OpenVPN



[Add VPN Configuration...](#)

2. Enter the required details and click "Done."
 1. Description: [Enter a description for this VPN connection]
 2. Server: [Enter the server address]
 3. Remote ID: [Enter the remote ID]
 4. Username: [Enter your VPN username]
 5. Password: [Enter your VPN password]
 6. Type: IKEv2

7. Proxy: Off

13:48

LTE

Cancel

Add Configuration

Done

Type

IKEv2 >

Description PuqCloud

Server dev.softkeel.com

Remote ID dev.softkeel.com

Local ID

AUTHENTICATION

User Authentication

Username >

Username user_3

Password


PROXY

Off

Manual

Auto

3. Finally, select the VPN you added and don't forget to toggle the switch to enable it.



4. By tapping on the (i) icon, you can check the information for this VPN or make any necessary changes

13:49

LTE

< VPN

PuqCloud

Edit

Type IKEv2

Server dev.softkeel.com

Account user_3

Server Address 77.87.125.200

Address 10.0.111.16

Address 2a11:ff00::111

Connect Time 0:14

Delete VPN

Revision #3

Created 31 July 2023 04:21:43 by Yuliia Noha

Updated 16 October 2023 02:04:17 by Yuliia Noha