

WHMCS Installation and Update

Mikrotik VPN module **WHMCS**

[Order now](#) | [Download](#) | [Community](#)

System requirements

Requirement	Minimum
WHMCS	8.x+, 9.x+
PHP	7.4, 8.1, 8.2, 8.3, 8.4
Mikrotik RouterOS	7.x or higher
ionCube Loader	v15+

“ **Note:** The module uses ionCube encoding. Make sure ionCube Loader is installed and active on your server.

Installation

“ **Note:** The module now uses **ionCube 15**, which provides universal out-of-the-box support for all encodings.

All versions can be found at this link:

https://download.puqcloud.com/WHMCS/servers/PUQ_WHMCS-Mikrotik-VPN/

Older module versions for WHMCS 8 are available in the archive directory:
`https://download.puqcloud.com/WHMCS/servers/PUQ_WHMCS-Mikrotik-VPN/archive/`

1. Download the latest version from the PUQ download page:

```
wget https://download.puqcloud.com/WHMCS/servers/PUQ_WHMCS-Mikrotik-VPN/PUQ_WHMCS-Mikrotik-VPN-latest.zip
```

2. Unzip the archive:

```
unzip PUQ_WHMCS-Mikrotik-VPN-latest.zip -d PUQ_WHMCS-Mikrotik-VPN-latest
```

3. Upload the module files to your WHMCS installation:

- For **Server modules**: copy the `puqMikrotikVPN` directory from the unzipped folder to `whmcs/modules/servers/`

```
cp -r PUQ_WHMCS-Mikrotik-VPN-latest/puqMikrotikVPN /path/to/whmcs/modules/servers/
```

4. The module files are now in place. Proceed to the configuration chapter to set up your Mikrotik router and WHMCS product.

Update

The update procedure is the same as installation — replace the existing files with the new version:

1. Download the latest version as described in the Installation section.
2. Unzip the archive.
3. For server modules: simply overwrite the files in `whmcs/modules/servers/puqMikrotikVPN/`. No deactivation is needed.
4. Verify the version number in the module interface matches the new release.

Revision #2

Created 22 September 2026 15:26:47 by Ruslan

Updated 22 September 2026 15:27:02 by Ruslan