

Product Configuration in WHMCS

Mikrotik WireGuard VPN module

WHMCS

[Order now](#) | [Download](#) | [FAQ](#)

Add new product to WHMCS

System Settings->Products/Services->Create a New Product

In the **Module settings** section, select the "**PUQ Mikrotik WireGuard VPN**" module

Details	Pricing	Module Settings	Custom Fields	Configurable Options	Upgrades	Free Domain	Cross-sells	Other	Links
<div> <div>Module Name</div> <div>PUQ Mikrotik WireGuard VPN</div> </div> <div> <div>Server Group</div> <div>None</div> </div>									
<div> <div>License key</div> <div>X3A1HN-CXCZVZ-JA7EOD-2NTT04-FOYCDK success: 2025-12-07T18:23:50+01:00</div> </div> <div> <div>WireGuard interface</div> <div>wireguard1 WireGuard interface on Mikrotik</div> </div>									
<div> <div>Peers configuration</div> <div> <div>Bandwidth Download:</div> <div>15</div> <div>M</div> </div> <div> <div>Bandwidth Upload:</div> <div>15</div> <div>M</div> </div> <div> <div>DNS Servers:</div> <div>8.8.8.8,1.1.1.1</div> </div> <div> <div>Allowed IPs:</div> <div>0.0.0.0/0</div> </div> <div> <div>Persistent Keepalive:</div> <div>60</div> </div> </div> <div> <div>Additional settings</div> <div> <div>Comment PREFIX:</div> <div>whmcs-dev</div> </div> <div> <div>Link to instruction:</div> <div>https://doc.puq.info/books/putvpcncp</div> <div>A link to the instruction will be reflected in the client area.</div> </div> <div> <div>Link to VPN clients:</div> <div>https://doc.puq.info/books/putvpcncp/page</div> <div>A link to the VPN clients.</div> </div> </div>									
<div> <div>Metric Billing</div> <div> <div>Bandwidth Usage In (GB)</div> <div>ON</div> <div>Configure Pricing</div> </div> <div> <div>Bandwidth Usage Out (GB)</div> <div>ON</div> <div>Configure Pricing</div> </div> </div>									

- **License key:** A pre-purchased license key for the "**PUQ Mikrotik WireGuard VPN**" module. For the module to work correctly, the key must be active
- **WireGuard interface:** A pre-created WireGuard server on a Mikrotik router, which will serve as peers for clients of this service.
- **Comment PREFIX:** The prefix that will be added to the VPN user's comment on the Mikrotik router
- **Bandwidth Download:** Download Bandwidth Limit in M/s
- **Bandwidth Upload:** Upload Bandwidth Limit M/s

- **DNS Servers:** Option in WireGuard client configuration
- **AllowedIPs:** Option in WireGuard client configuration
- **Persistent Keepalive:** Option in WireGuard client configuration
- **Link to instruction:** Link to the instruction, if filled out, it will be reflected in the client area
- **Link to VPN clients:** The URL that will be shown to the client in the client panel in order to download the VPN client

Metric Billing

It is also possible to set up tariffs for incoming and outgoing traffic.
 Standard methods for setting up metrics

Bandwidth Usage In

Configure Pricing

Bandwidth Usage In (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:

☐ Per Unit ⓘ
 ☒ Total Volume ⓘ
 ☐ Graduated ⓘ

Quantity Included

12

Starting Quantity ⓘ	Price Per GB			
	PLN	EUR	UAH	USD
0	1	2	3	4

Add Range

Close

Save

Bandwidth Usage Out

Configure Pricing

Bandwidth Usage Out (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:

☐ Per Unit ⓘ

☒ Total Volume ⓘ

☐ Graduated ⓘ

Quantity Included

11

Starting Quantity ⓘ	Price Per GB			
	PLN	EUR	UAH	USD
0	5	6	7	8

Add Range

Close

Save