

Product Configuration in WHMCS

Mikrotik WireGuard VPN module

WHMCS

[Order now](#) | [Download](#) | [FAQ](#)

Add new product to WHMCS

System Settings->Products/Services->Create a New Product

In the **Module settings** section, select the "**PUQ Mikrotik WireGuard VPN**" module

The screenshot shows the 'Module Settings' tab for the 'PUQ Mikrotik WireGuard VPN' module. The interface includes a top navigation bar with tabs: Details, Pricing, Module Settings (active), Custom Fields, Configurable Options, Upgrades, Free Domain, Cross-sells, Other, and Links. Below the tabs, the 'Module Name' is set to 'PUQ Mikrotik WireGuard VPN' and the 'Server Group' is set to 'None'. The main configuration area is divided into two columns. The left column contains the 'License key' (X3A1HN-CXCZVZ-JA7EOD-2NTT04-FOYCDK, success: 2025-12-07T18:23:50+01:00) and the 'Peers configuration' section with fields for 'Bandwidth Download' (15 M), 'Bandwidth Upload' (15 M), 'DNS Servers' (8.8.8.8,1.1.1.1), 'AllowedIPs' (0.0.0.0/0), and 'Persistent Keepalive' (60). The right column contains the 'WireGuard interface' (wireguard1) and the 'Additional settings' section with fields for 'Comment PREFIX' (whmcs-dev), 'Link to instruction' (https://doc.puq.info/books/putvncp), and 'Link to VPN clients' (https://doc.puq.info/books/putvncp/page). At the bottom, there are two sections for 'Metric Billing': 'Bandwidth Usage In (GB)' and 'Bandwidth Usage Out (GB)', both with 'ON' toggle switches and 'Configure Pricing' links. A 'Switch to Advanced Mode' link is located at the bottom right of the configuration area.

- **License key:** A pre-purchased license key for the "**PUQ Mikrotik WireGuard VPN**" module. For the module to work correctly, the key must be active
- **WireGuard interface:** A pre-created WireGuard server on a Mikrotik router, which will serve as peers for clients of this service.
- **Comment PREFIX:** The prefix that will be added to the VPN user's comment on the Mikrotik router
- **Bandwidth Download:** Download Bandwidth Limit in M/s
- **Bandwidth Upload:** Upload Bandwidth Limit M/s

- **DNS Servers:** Option in WireGuard client configuration
- **AllowedIPs:** Option in WireGuard client configuration
- **Persistent Keepalive:** Option in WireGuard client configuration
- **Link to instruction:** Link to the instruction, if filled out, it will be reflected in the client area
- **Link to VPN clients:** The URL that will be shown to the client in the client panel in order to download the VPN client

Metric Billing

It is also possible to set up tariffs for incoming and outgoing traffic.
 Standard methods for setting up metrics

Bandwidth Usage In

Configure Pricing

Bandwidth Usage In (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:

☐ Per Unit ⓘ
 ☒ Total Volume ⓘ
 ☐ Graduated ⓘ

Quantity Included

12

Starting Quantity ⓘ	Price Per GB			
	PLN	EUR	UAH	USD
0	1	2	3	4

Add Range

Close

Save

Bandwidth Usage Out

Configure Pricing

Bandwidth Usage Out (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Quantity Included

Scheme:

☐ Per Unit

☒ Total Volume

☐ Graduated

Starting Quantity

Price Per GB

PLN

EUR

UAH

USD

0

5

6

7

8

Add Range

Close

Save

Revision #5

Created 8 October 2023 21:11:16 by Ruslan

Updated 29 July 2024 15:06:29 by Ruslan