

# Product Configuration in WHMCS

## Mikrotik WireGuard VPN module

# WHMCS

[Order now](#) | [Download](#) | [FAQ](#)

### Add new product to WHMCS

System Settings->Products/Services->Create a New Product

In the **Module settings** section, select the "**PUQ Mikrotik WireGuard VPN**" module

Details	Pricing	Module Settings	Custom Fields	Configurable Options	Upgrades	Free Domain	Cross-sells	Other	Links
<div> <div>Module Name</div> <div>PUQ Mikrotik WireGuard VPN</div> </div> <div> <div>Server Group</div> <div>None</div> </div>									
<div> <div>License key</div> <div>X3A1HN-CXCZVZ-JA7EOD-2NTT04-FOYCDK success: 2025-12-07T18:23:50+01:00</div> </div> <div> <div>WireGuard interface</div> <div>wireguard1 WireGuard interface on Mikrotik</div> </div>									
<div> <div>Peers configuration</div> <div> <div>Bandwidth Download:</div> <div>15</div> <div>M</div> </div> <div> <div>Bandwidth Upload:</div> <div>15</div> <div>M</div> </div> <div> <div>DNS Servers:</div> <div>8.8.8.8,1.1.1.1</div> </div> <div> <div>AllowedIPs:</div> <div>0.0.0.0/0</div> </div> <div> <div>Persistent Keepalive:</div> <div>60</div> </div> </div> <div> <div>Additional settings</div> <div> <div>Comment PREFIX:</div> <div>whmcs-dev</div> </div> <div> <div>Link to instruction:</div> <div>https://doc.puq.info/books/puqvpnnp</div> <div>A link to the instruction will be reflected in the client area.</div> </div> <div> <div>Link to VPN clients:</div> <div>https://doc.puq.info/books/puqvpnnp/page</div> <div>A link to the VPN clients.</div> </div> </div>									
<div> <div>Metric Billing</div> <div> <div>Bandwidth Usage In (GB)</div> <div>ON</div> <div>Configure Pricing</div> </div> <div> <div>Bandwidth Usage Out (GB)</div> <div>ON</div> <div>Configure Pricing</div> </div> </div>									

- **License key:** A pre-purchased license key for the "**PUQ Mikrotik WireGuard VPN**" module. For the module to work correctly, the key must be active
- **WireGuard interface:** A pre-created WireGuard server on a Mikrotik router, which will serve as peers for clients of this service.
- **Comment PREFIX:** The prefix that will be added to the VPN user's comment on the Mikrotik router
- **Bandwidth Download:** Download Bandwidth Limit in M/s
- **Bandwidth Upload:** Upload Bandwidth Limit M/s

- **DNS Servers:** Option in WireGuard client configuration
- **AllowedIPs:** Option in WireGuard client configuration
- **Persistent Keepalive:** Option in WireGuard client configuration
- **Link to instruction:** Link to the instruction, if filled out, it will be reflected in the client area
- **Link to VPN clients:** The URL that will be shown to the client in the client panel in order to download the VPN client

## Metric Billing

It is also possible to set up tariffs for incoming and outgoing traffic.  
 Standard methods for setting up metrics

### Bandwidth Usage In

Configure Pricing

Bandwidth Usage In (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:

☐ Per Unit ⓘ
 ☒ Total Volume ⓘ
 ☐ Graduated ⓘ

Quantity Included

12

Starting Quantity ⓘ	Price Per GB			
	PLN	EUR	UAH	USD
0	1	2	3	4

Add Range

Close

Save

### Bandwidth Usage Out

Configure Pricing

Bandwidth Usage Out (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:

☐ Per Unit ⓘ

☒ Total Volume ⓘ

☐ Graduated ⓘ

Quantity Included

11

Starting Quantity ⓘ	Price Per GB			
	PLN	EUR	UAH	USD
0	5	6	7	8

Add Range

Close

Save