

# Order Detail

## MinIO S3 module **WISECP**

[Order now](#) | [Download](#) | [FAQ](#)

Navigate to the service you want to manage, then go to the '**Core**' tab.

Detail

Core

Blocks

+ Order Addons

Requirements

Upgrade / Downgrade

History

Cancellation / Refund

API Module

PUQ MiniO S3

Update Policy

Set Standard Policy

Set Limited Policy

API answer OK

User

Display Name	Status	Policy	Groups	Storage used	Storage free	Storage total
wise2-160cp	enabled	wise2-160cp	USER5	4.5514 GB (91.03%)	0.4486 GB (8.97%)	5 GB

Buckets

Bucket Name	Size	Objects	Creation date
wise2-160cp-default	0 GB	0	2024-05-14T23:43:00Z
wise2-160cp-default2	0.0001 GB	1	2024-05-14T23:44:07Z
wise2-160cp-default3	1.6055 GB	5	2024-05-14T23:44:30Z
wise2-160cp-default34	2.9458 GB	9	2024-05-14T23:44:17Z

Server

console.minio-test.uuq.pl

Username

wise2-160cp

Password

QWEqwe123

Overwrite package settings

☐ Overwriting the package settings is necessary to personalize the service if you need it.

Send changes to server

☐ To apply the changes on the server, it is necessary to check this checkbox.

Update

in the opened tab, you have a view of the online status of the service. The available online information includes:

- **Update Policy** button sets the required policy upon clicking, provided that the free space = 0, it sets a limited policy; otherwise, it sets the default policy
- **Set Standard Policy** button sets the standard policy
- **Set Limited Policy** button sets the limited policy
- Attention, automatic policy change process occurs once per hour, so after the policy is changed forcibly, the policy will return to the correct state.
- Connection status to the API

- Information about user account on the MinIO server
- Diagnostic information about the account
- List of buckets and their size and contents

Also, below are fields with the client's personal data, such as Username, Password, Server

You can also individually override package options for the client by checking the '**Override package settings**' box.

wise2-1b0cp-default	U uB	U	2024-05-14 12:54:300Z
wise2-160cp-default2	0.0001 GB	1	2024-05-14T23:44:07Z
wise2-160cp-default3	1.6055 GB	5	2024-05-14T23:44:30Z
wise2-160cp-default134	2.9458 GB	9	2024-05-14T23:44:17Z

Server

console.minio-test.uuq.pl

Username

wise2-160cp

Password

QWEqwe123

Server Group

Default (Servers: 1)

Disk Limit

5

in GB

Group

USERS

MinIOS3 group

Username prefix

wise

Will be attached to the beginning of username. Only small letters and numbers and symbol "-"

Username suffix

cp

Will be appended to the end of username. Only small letters and numbers and symbol "-"

Link to instruction

https://puqcloud.com/

A link to the instruction will be reflected in the client area.

Create default bucket

Yes

Once the user is created, a default bucket will be created.

Default bucket postfix

-default

Will be appended to the end of bucket name. Only small letters and numbers and symbol "-"

Raw policy

{  
 "Version": "2012-10-17",  
 "Statement": [  
 {  
 "Effect": "Allow",  
 "Principal": "MinIOS3 group",  
 "Action": "s3:\*"  
 }  
 ]  
}

Raw policy Disk limit

{  
 "Version": "2012-10-17",  
 "Statement": [  
 {  
 "Effect": "Allow",  
 "Principal": "MinIOS3 group",  
 "Action": "s3:\*"  
 }  
 ]  
}

<USER\_ID> - Macro to be replaced

Overwrite package settings

☒ Overwriting the package settings is necessary to personalize the service if you need it.

Send changes to server

☐ To apply the changes on the server, it is necessary to check this checkbox.

Update

Note: When changing the Server Group, Server fields, make sure you have a user with the username as specified in the 'Username' field pre-created on the new server. Otherwise, you will need to recreate the service for your client.