



# Add server (Nextcloud) in WISECP

## Nextcloud module **WISECP**

[Order now](#) | [Download](#) | [FAQ](#)

1. Log in to the administrative area of your **WISECP**.
2. Go to module configuration.

Services -> Service Management -> Module Settings -> Other -> All Modules -> PUQ Nextcloud



Other

- Initial Settings
- All Modules

OtherDashboard / Module Settings / Other

- Initial Settings
- All Modules

Search Within Modules

Write something...

- 
- 
- 
- 
- PUQ Nextcloud
- 
- 

3. In the opened page, click the 'Add Server' button.

OtherDashboard / Module Settings

- Initial Settings
- All Modules

PUQ Nextcloud



License key

GDSFNX- -UZAPKG

2024-01-08T16:11:39+01:00

Check and Save

Version: 1.0

Web Site

Documentation

Changelog

+ Add New Server

Server Groups

Servers [Nextcloud](#)

10 Show Record

Search

| # | Name                  | Status | Group   | Default | IP/Domain             | Usage Stats |  |
|---|-----------------------|--------|---------|---------|-----------------------|-------------|--|
| 8 | nextcloud-test.uuq.pl | active | Default | ✓       | nextcloud-test.uuq.pl | 1/10        |  |

Showing records from 1 to 1 - 1

Prev 1 Next

4. On the opened page, enter all the necessary information:

- **Name:** Displayed name of the server.
- **Maximum Number of Accounts:** The number of services that can be on this server.
- **Server Group:** Optionally, choose the server group.
- **IP Address or Domain:** The address of the Nextcloud server you are connecting to.
- **Username/Password:** Username and Password on the Nextcloud server.
- Check the **SSL** box if you want to use SSL-encrypted connection. If necessary, specify the port and perform a connection test.

Other

[Dashboard](#) / [Module Settings](#) / [Other](#)

Initial Settings

All Modules

PUQ Nextcloud

PUQcloud

Go to Back

Add New Server

Server Name

nextcloud-test.uuq.pl

Maximum Number of Accounts

112

Server Group

Default

Default

☐ Set as default server in group

IP Address or Domain

nextcloud-test.uuq.pl

Username

wiseadmin

Password

R

SSL

☒ Connect using SSL

Port

443

☐ Change standard port

Test Connection

Test Connection

Turn Back

Add New Server

Revision #1

Created 10 December 2023 12:58:28 by Ruslan

Updated 10 December 2023 13:03:24 by Ruslan