

Product Configuration

ownCloud module **WHMCS**

[Order now](#) | [Download](#) | [FAQ](#)

Add new product to WHMCS

System Settings->Products/Services->Create a New Product

In the **Module settings** section, select the "**PUQ ownCloud**" module

Edit Product

Details		Pricing		Module Settings		Custom Fields		Configurable Options		Upgrades		Free Domain		Cross-sells		Other		Links			
Module Name		PUQ ownCloud																			
Server Group		owncloud																			
License key		3165D1- -YIQC1Y success: 2024-04-03T13:25:13+02:00																			
Disk space size		2		in unit		Unit		GigaByte Unit of measure in the product													
Notification, used disk space X %		80		Notification disk limit email template		puqNextcloud Notification disk li															
Username suffix		-Cloud		Username prefix		own- Will be attached to the beginning of username. Only small letters and numbers and symbol "-"															
Save usage history (days)		0		Group		USERS20															
Client Area		Show Password:		Show button		Link to instruction https://puqcloud.com/ A link to the instruction will be reflected in the client area.															

- **License key:** A pre-purchased license key for the "**PUQ ownCloud**" module. For the module to work correctly, the key must be active
- **Unit:** Packet disk space units
- **Disk space size:** Disk size in this product
- **Notification disk limit email template:** Email template that will be sent when the disk quota is exceeded in %
- **Notification, used disk space X %:** Sets a percentage parameter, after exceeding this parameter a notification will be sent to the user
- **Username prefix/Username suffix:** Necessary in order to generate a username for the service, in the format: **prefix<client_id>-<service_id>suffix**
- **Group:** The group that will be assigned to the user on the server side of the **ownCloud**
- **Save usage history (days):** The number of days it takes to save user disk usage statistics
- **Link to instruction:** Link to the instruction, if filled out, it will be reflected in the client

area

- **Client Area:** Client zone settings, show or not show the password in the client zone, type how to show the password.

Revision #7

Created 4 March 2023 13:39:43 by Ruslan

Updated 9 June 2024 13:12:54 by Yuliia Noha