

# Product Configuration

## ownCloud module WHMCS

[Order now](#) | [Download](#) | [FAQ](#)

### Add new product to WHMCS

System Settings->Products/Services->Create a New Product

In the **Module settings** section, select the **"PUQ ownCloud"** module

Edit Product
Details
Pricing
Module Settings
Custom Fields
Configurable Options
Upgrades
Free Domain
Cross-sells
Other
Links

Module Name
PUQ ownCloud
Server Group
owncloud

License key
3165D1- -Y1QC1Y
success: 2024-04-03T13:25:13+02:00
Disk space size
2
in unit
Notification, used disk space X %
80
Username suffix
-Cloud
Will be appended to the end of username. Only small letters and numbers and symbol "-".
Save usage history (days)
0
0 - all history
Client Area
Show Password:
Show button
Show service password in the client area

Unit
GigaByte
Unit of measure in the product
Notification disk limit email template
puqNextcloud Notification disk li
Username prefix
own-
Will be attached to the beginning of username. Only small letters and numbers and symbol "-".
Group
USERS20
Link to instruction
https://puqcloud.com/
A link to the instruction will be reflected in the client area.

- **License key:** A pre-purchased license key for the **"PUQ ownCloud"** module. For the module to work correctly, the key must be active
- **Unit:** Packet disk space units
- **Disk space size:** Disk size in this product
- **Notification disk limit email template:** Email template that will be sent when the disk quota is exceeded in %
- **Notification, used disk space X %:** Sets a percentage parameter, after exceeding this parameter a notification will be sent to the user
- **Username prefix/Username suffix:** Necessary in order to generate a username for the service, in the format: **prefix<client\_id>-<service\_id>suffix**
- **Group:** The group that will be assigned to the user on the server side of the **ownCloud**
- **Save usage history (days):** The number of days it takes to save user disk usage statistics
- **Link to instruction:** Link to the instruction, if filled out, it will be reflected in the client

area

- **Client Area:** Client zone settings, show or not show the password in the client zone, type how to show the password.

---

Revision #7

Created 4 March 2023 13:39:43 by Ruslan

Updated 9 June 2024 13:12:54 by Yuliia Noha