

# Installation and configuration guide

- [Setup \(install/update\)](#)
- [License Activation](#)
- [Add server \(ownCloud\) in WISECP](#)
- [Service/Product configuration](#)

# Setup (install/update)

## ownCloud module **WISECP**

[Order now](#) | [Download](#) | [FAQ](#)

To install and update a module, you must perform one and the same action.

### 1. Download the latest version of the module.

```
wget http://download.puqcloud.com/WISECP/Product/PUQ_WISECP-ownCloud/PUQ_WISECP-ownCloud-latest.zip
```

All versions are available: [https://download.puqcloud.com/WISECP/Product/PUQ\\_WISECP-ownCloud/](https://download.puqcloud.com/WISECP/Product/PUQ_WISECP-ownCloud/)

### 2. Unzip the archive with the module.

```
unzip PUQ_WISECP-ownCloud-latest.zip
```

### 3. Copy and Replace "puqownCloud" from "PUQ\_WISECP-ownCloud" to "WISECP\_WEB\_DIR/coremio/modules/Product/"

# License Activation



## ownCloud module **WISECP**

[Order now](#) | [Download](#) | [FAQ](#)

1. Log in to the administrative area of your **WISECP**.

2. Go to module configuration.

Services -> Service Management -> Module Settings -> Other -> All Modules -> PUQ ownCloud



Other

- Initial Settings

All Modules

Other

Initial Settings

All Modules

Search Within Modules

Write something...

Q

PUQ ownCloud

3. On the open page, enter the purchased license key for this product and click the '**Check and Save**' button to validate the key and save it.

Dashboard / Module Settings / Other

Initial Settings

All Modules

PUQ ownCloud

PUQ cloud

License key

BMUJY MEQICG

2024-01-26T15:33:42+01:00

Check and Save

Version: 1.0

Web Site

Documentation

Changelog

Add New Server

Server Groups

Servers

ownCloud



# Add server (ownCloud) in WISECP

ownCloud module **WISECP**

[Order now](#) | [Download](#) | [FAQ](#)

1. Log in to the administrative area of your **WISECP**.
2. Go to module configuration.

Services -> Service Management -> Module Settings -> Other -> All Modules -> PUQ ownCloud



- **Name:** Displayed name of the server.
- **Maximum Number of Accounts:** The number of services that can be on this server.
- **Server Group:** Optionally, choose the server group.

- **IP Address or Domain:** The address of the ownCloud server you are connecting to.
- **Username/Password:** Username and Password on the ownCloud server.
- Check the **SSL** box if you want to use SSL-encrypted connection. If necessary, specify the port and perform a connection test.

Initial Settings

All Modules

PUQ ownCloud

PUQcloud

< Go to Back

Add New Server

Server Name	owncloud-test.uuq.pl
Maximum Number of Accounts	23
Server Group	Default
Default	<input type="checkbox"/> Set as default server in group
IP Address or Domain	IP address or Domain of a server
Username	admin
Password	adminpass
SSL	<input checked="" type="checkbox"/> Connect using SSL
Port	443 <input type="checkbox"/> Change standard port
Test Connection	<input type="button" value="Test Connection"/>

Add New Server

<< Turn Back

# Service/Product configuration

ownCloud module **WISECP**


[Order now](#) | [Download](#) | [FAQ](#)

If you do not have a **Service Group** where you want to place the new service, you need to create a new **Service Group**

1. Log in to the administrative area of your **WISECP**.
2. Create New Service Group

Go to

Services -> Service Management -> Add Group



Enter all the necessary data and click the '**Create Group**' button.



WISECP

Smart Search

SettingsOrdersBillingClientsToolsWAnalyticsSupportServicesSite ManagementLanguagesHelp

Create New Service Group

Dashboard / Create New Service Group

Create a new service group, you can also create new categories and manage the existing one from here.

ENUKROPTPLNLLVKAITIDHUFRAFAESELEDECSBSAR

Title

Storage

Short Detail

Short Group Description

Listing Template

☒ Box List ☐ Horizontal List

Status

Enable

Background Image

(optional)

Group Colour

#FFFFFF

Order Upgrades

☐ Allow clients to upgrade to higher package in the same service group

External HTML Code

Paste your HTML code to this field (Optional)

You can optionally add external HTML code and customize it. There should not be any incorrect or incomplete HTML codes, otherwise page structure will be empty

### 3. Adding a New Service

Go to

Services -> our service group where you need to add the new service.

WISECP

Smart Search

SettingsOrdersBillingClientsToolsWAnalyticsSupportServicesSite ManagementLanguagesHelp

€0  
Today Sales (Turnover)  
Yesterday

1  
Current Cash  
Current Month Expense

0  
Overdue Invoice  
(Total €0)

0  
Payment Date  
(Total €0 / Last 7 Days)

0  
Order in the  
(Total €0)

Service Management  
Hosting Management  
Domain Name Registration  
Software Services  
International SMS Services  
Google SEO Services  
VPN  
Media  
Storage

Recent Orders (Last 5)

In the opened window, click the 'Create New Service' button.

Storage

+ Create New Service

Categories

Service Group Settings

Apply to selected

10

Show Record

On the opened page, enter all the necessary details for your new service and navigate to the 'Core' tab.

Select the '**PUQ ownCloud**' module from the drop-down list of modules.

Add Service Pack For Storage

Dashboard / Storage / Add Service Product

Detail

Core

Optional Addons

Requirements

Upgradeable Products

Pricing

Module

PUQ ownCloud

Server Group

Default (Servers: 1)

Disk Limit

5 in GB

Group

USERS

ownCloud group

Username prefix

puq

Will be attached to the beginning of username. Only small letters and numbers and symbol "-"

Username suffix

cloud

Will be appended to the end of username. Only small letters and numbers and symbol "-"

Link to instruction

https://\*\*\*\*\*.\*/

A link to the instruction will be reflected in the client area.

Automatic Setup

Please activate for automatic installation of the order. Otherwise, administrator approval is required.

Create Product

#### 4. Fill in the configuration options according to your preferences.

- **Server Group** is the group of servers from which a server will be chosen for provisioning the service
- **Disk Limit:** is the disk space quota that is issued to the user
- **Group:** is the group that will be assigned to the user
- **Username Prefix** will be added at the beginning of the username during user creation and is used for uniqueness
- **Username Suffix** will be added at the end of the username during user creation and is also used for uniqueness
- **Link to Instruction** Provide the link to the instruction for the service, and it will be displayed in the client area as a separate button
- **Link to VPN Clients** Provide the link to the page for downloading VPN clients for the

service, and it will be displayed in the client area as a separate button

- **Automatic Setup** Please activate for automatic installation of the order. Otherwise, administrator approval is required.