

Advanced settings

[Order now](#) | [Download](#) | [FAQ](#)

For more precise server settings, you can use Advanced settings

On this page you can customize the server to suit your needs.

Use the official strongSwan documentation for parameter information

<https://wiki.strongswan.org/projects/strongswan/wiki/IpsecConf>

Go to menu item **VPN servers** -> **IKEv2** Click on the **Advanced settings** button

PUQVPNCP ? HELP ? ruslan (79.184.3.204) Logout

Dashboard

VPN servers

WireGuard

IKEv2

VPN accounts

Settings

About us

IKEv2

Save Advanced settings

IKEv2 Enabled
YES

Starter: PID: 2106159

Charon: PID: 2106160

ROOT certificate
certificate trusted, lifetimes valid
Delete ROOT certificate

SERVER certificate
certificate trusted, lifetimes valid
Delete SERVER certificate

ROOT certificate certificate trusted, lifetimes valid
Download CA certificate Download CA key

subject: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
issuer: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
validity: not before Dec 05 12:32:38 2022, ok
not after Dec 02 12:32:38 2032, ok (expires in 3642 days)
serial: 31:86:4b:df:10:2f:81:fc
flags: CA CRLSign self-signed
subjkeyId: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60
pubkey: RSA 4096 bits
keyid: 34:92:a9:5d:0f:00:a0:65:c0:39:2a:33:b1:b8:ed:92:e4:ce:2e:11
subjkey: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60

SERVER certificate info certificate trusted, lifetimes valid

subject: "CN=dev.softkeel.com, O=dev.softkeel.com, OU=TEST_OU, L=TEST_L, S=TEST_S, C=TEST_S"
issuer: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
validity: not before Dec 13 10:37:44 2022, ok
not after Dec 12 10:37:44 2027, ok (expires in 1824 days)
serial: 10:a4:8f:79:21:ec:b2:e8
altNames: dev.softkeel.com, 77.87.125.200
flags: serverAuth ikeIntermediate
authkeyId: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60
subjkeyId: d6:47:a2:4f:8f:2b:78:66:a7:d2:c6:77:ae:fb:71:47:e2:9f:46:79
pubkey: RSA 4096 bits
keyid: 8c:3f:a3:99:b7:45:7a:ed:d9:cb:b4:1c:a5:8b:97:f6:a0:e3:ee:93
subjkey: d6:47:a2:4f:8f:2b:78:66:a7:d2:c6:77:ae:fb:71:47:e2:9f:46:79

Go to the IKEv2 Advanced settings page

[Dashboard](#)
[VPN servers](#)
[VPN accounts](#)
[Settings](#)
[About us](#)

IKEv2 / Advanced settings

[Save and restart](#)
[Set default and reset](#)

config setup

Uniqueids:	no	▼
Strictcrpolicy:	no	▼

charondebug

how much charon debugging output should be logged

dmn:	0 (audit)	▼
mgr:	0 (audit)	▼
ike:	0 (audit)	▼
chd:	0 (audit)	▼
job:	0 (audit)	▼
cfg:	0 (audit)	▼
kn1:	0 (audit)	▼
net:	0 (audit)	▼
asn:	0 (audit)	▼
enc:	0 (audit)	▼
lib:	0 (audit)	▼
esp:	0 (audit)	▼
tls:	0 (audit)	▼
tnc:	0 (audit)	▼
imc:	0 (audit)	▼
imv:	0 (audit)	▼
pts:	0 (audit)	▼

conn default

Authby:	pubkey	▼
Closeaction:	none	▼
Compress:	no	▼
Dpddelay:	300	
Dpdtimeout:	150	
Inactivity:	86400	
Esp:	aes256-sha256,chac	
Forceencaps:	yes	▼
Fragmentation:	yes	▼
Ike:	aes256-sha1-modp1	
Ikelifetime:	86400	
Installpolicy:	yes	▼
Keyingtries:	5	
Lifetime:	3600	
Margintime:	600	
Mobike:	yes	▼
Modeconfig:	pull	▼
Reauth:	yes	▼
Rekey:	no	▼
Rekeyfuzz:	100	
Type:	tunnel	▼

In order to restore the default settings, click the **Set default and reset** button

Revision #6

Created 13 December 2022 09:42:15 by Ruslan

Updated 16 October 2023 08:58:26 by Yuliia Noha