

# iOS WireGuard client configuration

WireGuard Business-VPN module **WISECP**

[Order now](#) | [Download](#) | [FAQ](#)

In order to connect to a VPN, follow these steps:

1. Open the link you received in a browser to get instructions and configuration for your new VPN connection. And you will see the following page in the browser window

## This is a one-time link with configuration options

### WireGuard

[Download client Android](#)[Download client iOS](#)[Download client Windows](#)[Download client macOS](#)[Official clients WireGuard](#)[Download config file](#)

```
[Interface]
Address = 10.0.111.16/24,2a11:ff00::111/120
DNS = 10.0.111.1,2a11:ff00::101,2a11:ff00::8
PrivateKey = G0mgdb66DPex6YdP2/A4YDGtoAdAllgVAPsyhm1H0eB=

[Peer]
PersistentKeepalive = 25
Endpoint = dev.softkeel.com:51030
PublicKey = xbrwVfhnZ80sJH0yyzFwm0Ey1UC+vvKQ8FG/cLoJh2w=
AllowedIPs = 0.0.0.0/0, ::/0
```

### IKEv2

[Download Certificate CA](#)

**Server:** dev.softkeel.com

**Username:** user\_3

**Password:** dupa

[Download Profile](#)

2. Since we are setting up a connection for an iOS device, we need the WireGuard client for iOS. To download the client on your phone, open the link on your mobile device and click "Download client iOS".

**This is a one-time link with configuration options**

---

## **WireGuard**

Download client Android

Download client iOS

Download client Windows

Download client macOS

Official clients WireGuard



3. After you click on the "Download client iOS" button, your application store will open, where you need to install your client for iOS. Click "Install" to install the application on your mobile device.

12:33

LTE

< Search



# WireGuard

Fast, modern, secure VPN



26 RATINGS

4.2



AGE

4+

Years Old

CATEGORY



Utilities

## What's New


Version 1.0.16

Small bug fixes.

[Version History](#)

5mo ago

## Preview



4. After completing the app installation, open the app to configure your VPN connection.

12:33

LTE

< Search



# WireGuard

Fast, modern, secure VPN

OPEN



26 RATINGS

4.2



AGE

4+

Years Old

CATEGORY



Utilities

## What's New


Version 1.0.16

Small bug fixes.

[Version History](#)

5mo ago

## Preview



5. This is how the main window of the application looks like, which has no configured connections. To set up a new VPN connection, you must press the plus button or "Add a tunnel" button.

12:22 

 LTE 

Settings

WireGuard



Add a tunnel

6. After you click on the button that allows you to create a new connection, you will be presented with several options. Now we will use the QR code scanning method. Click on the "SCAN FROM QR CODE" button to start scanning.

Later in this manual, **in point number 10**, we will look at creating a connection using a configuration file.

12:22 

 LTE 

Settings

WireGuard



Add a tunnel

Add a new WireGuard tunnel

Create from file or archive


Create from QR code

Create from scratch

It is worth noting that if you are using the application for the first time, your device will ask you if you can allow access to the camera. You need to allow access to the camera, otherwise scanning will not be possible.

7. After you can already start scanning and see that your device is ready, point your camera at the QR code you received.

It is worth noting the system will ask your password



8. After scanning the code, when the scan was successful, the application will prompt you to enter a name for the new connection. Enter a name and save the new configuration by clicking on the "Save" button.

12:22

LTE

Scan QR code

Cancel

Download client macOS

Please name the  
scanned tunnel

Cancel

Save

q

w

e

r

t

y

u

i

o

p

a

s

d

f

g

h

j

k

l

↵

z

x

c

v

b

n

m

⌫

9. After you save your new connection, you will see a list of your VPN connections. Find the required connection to activate it and switch the slider to activation mode.

12:23 



◀ Settings

Settings

WireGuard



dev.softkeel.com



## 10. **To create a connection using a configuration**

**file:** You need to download the configuration file to your mobile device. To download this file, click on the "Download config file" button.

12:47

LTE

**This is a one-time link with configuration options**

## WireGuard

Download client Android

Download client iOS

Download client Windows

Download client macOS


Official clients WireGuard



Download config file



11. Once your configuration file has been downloaded to your device, you need to proceed. You need to return to the "WireGuard" application to import your configuration file. Click "Create from file or archive" to start importing the configuration file.



12. Next, you will be prompted to find your configuration file. You need to find the configuration file and select it.

13:15

LTE

Recents



Cancel

Search



wg0

12:47

319 bytes



jpg2png.zip

19/06/2023

70 KB



11\_new\_2019


-2020.zip



12/05/2020

12 MB

13. After you select your configuration file, the connection will be created.
14. To connect to a new VPN connection, you need to activate the slider opposite to the activate position.

12:47 

VPN

Settings

WireGuard



dev.softkeel.com



wg0



---

Revision #2

Created 25 November 2023 22:16:09 by Ruslan

Updated 25 November 2023 22:17:39 by Ruslan