

Service/Product configuration

WireGuard Business-VPN module **WISECP**

[Order now](#) | [Download](#) | [FAQ](#)

If you do not have a **Service Group** where you want to place the new service, you need to create a new **Service Group**

1. Log in to the administrative area of your **WISECP**.
2. Create New Service Group

Go to

Services -> Service Management -> Add Group

The screenshot displays the WISECP administrative dashboard. At the top, there is a navigation bar with the WISECP logo and a search bar. Below the navigation bar, there are several menu items: Settings, Orders (5), Billing, Clients, Tools, WAnalytics, Support, Services, Site Management, Languages, and Help. The 'Services' menu item is highlighted, and a dropdown menu is visible, showing options: Service Management, Hosting Management, Domain Name Registration, Software Services, Add Group (underlined in red), Module Settings, Addons, and Order Requirements. On the left side of the dashboard, there are two summary cards: 'Today Sales (Turnover)' showing €0 for yesterday, and 'Current Cash' showing €0 for the current month expenses.

Enter all the necessary data and click the 'Create Group' button.

The screenshot shows the 'Create New Service Group' form in the WISECP dashboard. The form includes the following fields and options:


- Title:** VPN
- Short Detail:** Short Group Description
- Listing Template:** Box List Horizontal List
- Status:** Enable
- Background Image:** (optional) [Image upload area]
- Group Colour:** #FFFFFF
- Order Upgrades:** Allow clients to upgrade to higher package in the same service group
- External HTML Code:** Paste your HTML code to this field (Optional)

At the bottom of the form, there is a note: "You can optionally add external HTML code and customize it. There should not be any incorrect or incomplete HTML codes, otherwise page structure will be empty".

3. Adding a New Service

Go to

Services -> our service group where you need to add the new service.



In the opened window, click the 'Create New Service' button.

VPN

+ Create New Service Categories Service Group Settings

Apply to selected
10 Show Record

Service	Category	Amount
---------	----------	--------

On the opened page, enter all the necessary details for your new service and navigate to the 'Core' tab.

Select the 'PUQ WireGuard Business-VPN' module from the drop-down list of modules.

Detail Core **+ Optional Addons** Requirements Upgradeable Products Pricing Active Services

Module: PUQ WireGuard Business-VPN

Server Group	Default (Servers: 1)	Number of VPN users	5
Bandwidth Download	5 in megabits (M)	Bandwidth Upload	5 in megabits (M)
Username prefix	wisecp- <small>Will be attached to the beginning of username. Only small letters and numbers and symbol "-"</small>	Username suffix	-puq <small>Will be appended to the end of username. Only small letters and numbers and symbol "-"</small>
Use main Public IP Address	<input type="checkbox"/> Use one main public IP for all services	Internal traffic	<input checked="" type="checkbox"/> Allow internal traffic
Enable IKEv2	<input checked="" type="checkbox"/> To enable the IKEv2 protocol	Persistent Keepalive	25
Interface MTU	1500	AllowedIPs	0.0.0.0/0
Link to instruction	https://puqcloud.com/ <small>A link to the instruction will be reflected in the client area.</small>	Link to VPN clients	https://puqcloud.com/ <small>A link to the instruction will be reflected in the client area.</small>

Automatic Setup Please activate for automatic installation of the order. Otherwise, administrator approval is required.

[Edit Product](#)

4. Fill in the configuration options according to your preferences.

- **Server Group** is the group of servers from which a server will be chosen for provisioning the service
- **Number of VPN Accounts:** the quantity of VPN user accounts a client can create within this package
- **Bandwidth Download** and **Bandwidth Upload** represent the connection speed that will be restricted by these parameters, in megabits per second, respectively.
- **Username prefix:** Will be attached to the beginning of username. Only small letters and numbers and symbol "-"
- **Username suffix:** Will be appended to the end of username. Only small letters and numbers and symbol "-"
- **Use main Public IP Address:** Use one main public IP for all services

- **Internal Traffic:** If the checkbox is selected, it indicates that internal traffic between VPN clients of the client will be allowed.
- **Persistent Keepalive/AllowedIPs:** parameters of configuration WireGuard clients
- **Interface MTU:** This parameter will be set during the creation of the WireGuard interface.
- **Link to Instruction** Provide the link to the instruction for the service, and it will be displayed in the client area as a separate button
- **Link to VPN Clients** Provide the link to the page for downloading VPN clients for the service, and it will be displayed in the client area as a separate button

Revision #2

Created 25 November 2023 15:06:55 by Ruslan

Updated 25 November 2023 15:10:49 by Ruslan