

# Product Configuration

## WireGuard VPN module **WHMCS**

[Order now](#) | [Download](#) | [FAQ](#)

### Add new product to WHMCS

System Settings->Products/Services->Create a New Product

In the **Module settings** section, select the **"PUQ WireGuard VPN"** module

- **License key:** A pre-purchased license key for the **"PUQ WireGuard VPN"** module. For the module to work correctly, the key must be active

**VPN Server**

VPN Server

Please select your server from the list. The list is loaded inconsistently from the server, you may need to log in to the panel to make changes.

- Please select your server from the list. The list is loaded inconsistently from the server

**Link settings**

Link to instruction

<https://doc.puq.info/books/wireguard-vpn-whmcs-module/page/description>

A link to the instruction will be shown in the client area.

Link to VPN clients

<https://www.wireguard.com/install/>

A link to the VPN clients will be shown in the client area.

- **Link to instruction** - If you have prepared instructions for your customers on how to use the service, then a link to the instructions is provided here (If filled, it will be shown in the client area)
- **Link to VPN clients** - Link to download the VPN client. For example <https://www.wireguard.com/install/> (If filled, it will be shown in the client area)
- **Disable One-time link** - When this option is enabled, a one-time link to the VPN clients will be disabled in the client area, preventing the customer from using a single-use link for downloading the VPN clients.

**E-mail configuration**

- **Custom Welcome Email** - Drop-down list of available e-mail templates for the action of creating a new client account. Please note that it is necessary to disable the standard welcome email in order to avoid double notification
- **Custom Change localization Email** - Drop-down list of available e-mail templates for the localization change action (package change) for the client account. Please note that

**User**

Username rule

Username template using macros.

Base macros:

- {client\_id} - Client ID
- {random\_digit\_x} - Random digits, where x is length (example: {random\_digit\_4})
- {random\_letter\_x} - Random letters (A-Z, a-z), where x is length (example: {random\_letter\_6})

Date & time macros:

- {unixtime}, {year}, {month}, {day}, {hour}, {minute}, {second}

Example:

{client\_id}-{service\_id}-{random\_digit\_4}

12-1234567890QWERTYUIOP[ASDFGHJKL"ZYCVBNM<qwertyuiop[]asdfghjkl;zyxcvbnm,./!@%&\*()\_+`

Password generator rule in format: length:char set.

Example:

67890

This will generate a 12-character password using the provided characters.

you need to disable the standard package change email to avoid double notification.

## VPN users settings

- **Bandwidth Download** - Bandwidth Download of VPN accounts (**package change**)
- **Bandwidth Upload** - BandwidthUpload of VPN accounts (**package change**)

## Metric Billing

**Configure Pricing**

Bandwidth Usage In (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:  Per Unit  Total Volume  Graduated

Quantity Included: 0.00

Price Per GB			
PLN	EUR	UAH	USD
17.00	10.00	150.00	9.00

Close Save

**Configure Pricing**

Bandwidth Usage Out (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:  Per Unit  Total Volume  Graduated

Quantity Included: 0.00

Price Per GB			
PLN	EUR	UAH	USD
18.00	10.00	150.00	9.00

Close Save

- **Bandwidth Usage In (GB):**
  - **Metric Type:** Monthly
  - **Metric Unit:** Gigabytes (GB)
  - **Pricing Scheme:**
    - **Per Unit:** Billing for each gigabyte of traffic.
    - **Total Volume:** Billing for the total volume of traffic.
    - **Graduated:** Billing on a graduated scale.
  - **Quantity Included:** Allows you to set how many gigabytes are included in the plan.
  - **Price Per GB:** Allows you to specify the cost per gigabyte of traffic in various

currencies.

- **Bandwidth Usage Out (GB):**

- **Metric Type:** Monthly
- **Metric Unit:** Gigabytes (GB)
- **Pricing Scheme:**
  - **Per Unit:** Billing for each gigabyte of traffic.
  - **Total Volume:** Billing for the total volume of traffic.
  - **Graduated:** Billing on a graduated scale.
- **Quantity Included:** Allows you to set how many gigabytes are included in the plan.
- **Price Per GB:** Allows you to specify the cost per gigabyte of traffic in various currencies.

## Overages Billing

Overages Billing	<input checked="" type="checkbox"/> Check to Enable	
Soft Limits	Disk Usage <input type="text" value="0"/> MB	Bandwidth <input type="text" value="1"/> GB
Overage Costs	Disk Usage <input type="text" value="0.0000"/>	Bandwidth <input type="text" value="10.0000"/> (Price Per Unit Over Above)

- **Check to Enable:** Enables overage billing.
- **Soft Limits:**
  - **Disk Usage:** not use.
  - **Bandwidth:** Sets a soft limit for bandwidth usage (units: MB, GB, TB). For example, you can set a soft limit of 1 GB for bandwidth.
- **Overage Costs:**
  - **Disk Usage:** not use.
  - **Bandwidth:** Specifies the cost per unit over the soft limit for bandwidth usage.
  - **Price Per Unit Over Above:** Sets the pricing for overage units.

---

Revision #17

Created 25 November 2022 03:30:10 by Ruslan

Updated 5 February 2026 06:16:39 by Dmytro Kravchenko