

Create a server certificate

[Order now](#) | [Download](#) | [FAQ](#)

Before creating a server certificate, you must create or import a root certificate.

Go to menu item **VPN servers -> IKEv2**

PUQVPNCP ? HELP ? ruslan (79.184.3.204) Logout

Dashboard

VPN servers

- WireGuard
- IKEv2**

VPN accounts

Settings

About us

IKEv2

[Save](#) [Advanced settings](#)

IKEv2 Enabled
NO

Starter: **not running**
Charon: **not running**

ROOT certificate
certificate trusted, lifetimes valid

[Delete ROOT certificate](#)

SERVER certificate
Certificate failed

Server Domain*
dev.softkeel.com

Server IP*
77.87.125.200

Common name*
dev.softkeel.com

Organization*
dev.softkeel.com

Organizational Unit
TEST_OU

Locality
TEST_L

State or Province Name
TEST_S

Country Name
TEST_S

[Generate SERVER certificate](#)

ROOT certificate certificate trusted, lifetimes valid

[Download CA certificate](#) [Download CA key](#)

```
subject: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
issuer: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
validity: not before Dec 05 12:32:38 2022, ok
not after Dec 02 12:32:38 2032, ok (expires in 3642 days)
serial: 31:86:4b:df:10:2f:81:fc
flags: CA CRLSign self-signed
subjkeyId: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60
pubkey: RSA 4096 bits
keyid: 34:92:a9:5d:0f:00:a0:65:c0:39:2a:33:b1:b8:ed:92:e4:ce:2e:11
subjkey: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60
```

SERVER certificate info Certificate failed

You need to fill in the required fields such as:

- **Server Domain**
- **Server IP**
- **Common name**
- **Organization**

Then click the button **Generate SERVER certificate**

After these steps, the **Server certificate and private key** will be generated.
Information about the certificate will be available in the same place.

PUQVPNCP ? HELP ? ruslan (79.184.3.204) Logout

Dashboard VPN servers VPN accounts Settings About us

IKEv2

Successfully ×

IKEv2 Enabled

YES

Starter: PID: **2106159**

Charon: PID: **2106160**

ROOT certificate
certificate trusted, lifetimes valid

Delete ROOT certificate

SERVER certificate
certificate trusted, lifetimes valid

Delete SERVER certificate

ROOT certificate certificate trusted, lifetimes valid

Download CA certificate Download CA key

```

subject: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
issuer: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
validity: not before Dec 05 12:32:38 2022, ok
not after Dec 02 12:32:38 2032, ok (expires in 3642 days)
serial: 31:86:4b:df:10:2f:81:fc
flags: CA CRLSign self-signed
subjKeyId: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60
pubkey: RSA 4096 bits
keyid: 34:92:a9:5d:0f:00:a0:65:c0:39:2a:33:b1:b8:ed:92:e4:ce:2e:11
subjkey: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60

```

SERVER certificate info certificate trusted, lifetimes valid

```

subject: "CN=dev.softkeel.com, O=dev.softkeel.com, OU=TEST OU, L=TEST_L, S=TEST_S, C=TEST_S"
issuer: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
validity: not before Dec 13 10:37:44 2022, ok
not after Dec 12 10:37:44 2027, ok (expires in 1824 days)
serial: 10:a4:8f:79:21:ec:b2:e8
altNames: dev.softkeel.com, 77.87.125.200
flags: serverAuth ikeIntermediate
authkeyId: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60
subjKeyId: d6:47:a2:4f:8f:2b:78:66:a7:d2:c6:77:ae:fb:71:47:e2:9f:46:79
pubkey: RSA 4096 bits
keyid: 8c:3f:a3:99:b7:45:7a:ed:d9:cb:b4:1c:a5:8b:97:f6:a0:e3:ee:93
subjkey: d6:47:a2:4f:8f:2b:78:66:a7:d2:c6:77:ae:fb:71:47:e2:9f:46:79

```

To remove the server certificate, use the **Delete SERVER certificate** button

After a successful server certificate generation process, the IKEv2 server transitions to the enabled state.

IKEv2 Enabled

YES

Starter: PID: **2106159**

Charon: PID: **2106160**

Revision #7

Created 13 December 2022 09:34:08 by Ruslan

Updated 16 October 2023 08:58:22 by Yuliia Noha