

Create a server certificate

[Order now](#) | [Download](#) | [FAQ](#)

Before creating a server certificate, you must create or import a root certificate.

Go to menu item **VPN servers -> IKEv2**

PUQVPNCP ? HELP ? ruslan (79.184.3.204) Logout

Dashboard

VPN servers

WireGuard

IKEv2

VPN accounts

Settings

About us

IKEv2

Save Advanced settings

IKEv2 Enabled
NO

Starter: **not running**
Charon: **not running**

ROOT certificate
certificate trusted, lifetimes valid

Delete ROOT certificate

SERVER certificate
Certificate failed

Server Domain*
dev.softkeel.com

Server IP*
77.87.125.200

Common name*
dev.softkeel.com

Organization*
dev.softkeel.com

Organizational Unit
TEST_OU

Locality
TEST_L

State or Province Name
TEST_S

Country Name
TEST_S

Generate SERVER certificate

ROOT certificate certificate trusted, lifetimes valid

Download CA certificate Download CA key

subject: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
issuer: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"
validity: not before Dec 05 12:32:38 2022, ok
not after Dec 02 12:32:38 2032, ok (expires in 3642 days)
serial: 31:86:4b:df:10:2f:81:fc
flags: CA CRLSign self-signed
subjkeyId: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60
pubkey: RSA 4096 bits
keyid: 34:92:a9:5d:0f:00:a0:65:c0:39:2a:33:b1:b8:ed:92:e4:ce:2e:11
subjkey: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60

SERVER certificate info Certificate failed

You need to fill in the required fields such as:

- **Server Domain**
- **Server IP**
- **Common name**
- **Organization**

Then click the button **Generate SERVER certificate**

After these steps, the **Server certificate and private key** will be generated.
Information about the certificate will be available in the same place.

PUQVPNCP

? HELP ?

ruslan (79.184.3.204)

Logout

Dashboard

VPN servers

VPN accounts

Settings

About us

IKEv2

Save Advanced settings

IKEv2 Enabled

YES

Starter: PID: 2106159

Charon: PID: 2106160

ROOT certificate

certificate trusted, lifetimes valid

Delete ROOT certificate

SERVER certificate

certificate trusted, lifetimes valid

Delete SERVER certificate

ROOT certificate certificate trusted, lifetimes valid

Download CA certificate Download CA key

subject: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"

issuer: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"

validity: not before Dec 05 12:32:38 2022, ok

not after Dec 02 12:32:38 2032, ok (expires in 3642 days)

serial: 31:86:4b:df:10:2f:81:fc

flags: CA CRLSign self-signed

subjkeyId: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60

pubkey: RSA 4096 bits

keyid: 34:92:a9:5d:0f:00:a0:65:c0:39:2a:33:b1:b8:ed:92:e4:ce:2e:11

subjkey: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60

SERVER certificate info certificate trusted, lifetimes valid

subject: "CN=dev.softkeel.com, O=dev.softkeel.com, OU=TEST OU, L=TEST_L, S=TEST_S, C=TEST_S"

issuer: "CN=PUQ VPN, O=PUQ sp. z o.o., OU=PUQ VPN, L=Warszaw, C=PL"

validity: not before Dec 13 10:37:44 2022, ok

not after Dec 12 10:37:44 2027, ok (expires in 1824 days)

serial: 10:a4:8f:79:21:ec:b2:e8

altNames: dev.softkeel.com, 77.87.125.200

flags: serverAuth ikeIntermediate

authkeyId: 56:c2:cc:8f:a3:d4:c7:7c:36:31:b5:a4:23:ea:fa:4b:0e:d0:c8:60

subjkeyId: d6:47:a2:4f:8f:2b:78:66:a7:d2:c6:77:ae:fb:71:47:e2:9f:46:79

pubkey: RSA 4096 bits

keyid: 8c:3f:a3:99:b7:45:7a:ed:d9:cb:b4:1c:a5:8b:97:f6:a0:e3:ee:93

subjkey: d6:47:a2:4f:8f:2b:78:66:a7:d2:c6:77:ae:fb:71:47:e2:9f:46:79

To remove the server certificate, use the **Delete SERVER certificate** button

After a successful server certificate generation process, the IKEv2 server transitions to the enabled state.

IKEv2 Enabled

YES

Starter: PID: 2106159

Charon: PID: 2106160

Revision #7

Created 13 December 2022 09:34:08 by Ruslan

Updated 16 October 2023 08:58:22 by Yuliia Noha