

Product Configuration

WireGuard Business-VPN module **WHMCS**

[Order now](#) | [Download](#) | [FAQ](#)

Add new product to WHMCS

System Settings->Products/Services->Create a New Product

In the **Module settings** section, select the "**PUQ WireGuard Business-VPN**" module

License key	5MZIQA- [REDACTED] JDXAWN success: 2023-12-21T10:36:12+01:00
WireGuard configuration	WireGuard server configuration Public IP for all services: <input checked="" type="checkbox"/> Public IP: <input type="text" value="77.87.125.200"/> Use this IP address Allow internal traffic: <input checked="" type="checkbox"/> DNS 1: <input type="text" value="8.8.8.8"/> DNS 2: <input type="text" value="1.1.1.1"/> Persistent Keepalive: <input type="text" value="25"/> Enable IKEv2: <input checked="" type="checkbox"/> To enable the IKEv2 protocol
VPN users settings	VPN users settings Number of VPN users: <input type="text" value="5"/> Bandwidth Download: <input type="text" value="3"/> M Bandwidth Upload: <input type="text" value="4"/> M Link to instruction: <input type="text" value="https://doc.puq.info/books/puqvpnc"/> A link to the instruction will be reflected in the client area. Link to VPN clients: <input type="text" value="https://www.wireguard.com/install/"/> A link to the VPN clients will be reflected in the client area.

- **License key:** A pre-purchased license key for the "**PUQ WireGuard Business-VPN**" module. For the module to work correctly, the key must be active

WireGuard configuration

- **Public IP for all services** - If you want to assign one public IP address to all services (IP must be configured on the **PUQVPNCP** server)
- **Public IP** - If you want to assign one public IP address to all services (IP must be configured on the **PUQVPNCP** server)
- **Allow internal traffic**- If you want to enable traffic exchange between VPN clients **[REDACTED]** **(package change)**
- **DNS1, DNS2** - DNS servers if they differ from the configuration in the **PUQVPNCP** panel **[REDACTED]** **(package change)**

VPN users settings

- **Number of VPN users** - Number of vpn accounts per service **(package change)**
- **Bandwidth Download** - Bandwidth Download of VPN accounts **(package change)**
- **Bandwidth Upload**- BandwidthUpload of VPN accounts **(package change)**
- **Link to instruction**- If you have prepared instructions for your customers on how to use the service, then a link to the instructions is provided here (If filled, it will be shown in the client area)
- **Link to VPN clients**- Link to download the VPN client. For example <https://www.wireguard.com/install/> (If filled, it will be shown in the client area)
- **Persistent Keepalive**- sets the Keepalive parameter in the WireGuard server client configuration **(package change)**
- **Enable IKEv2**- Enable IKEv2 protocol support **(package change)**

Revision #10

Created 24 November 2022 09:17:21 by Ruslan

Updated 11 June 2024 03:01:06 by Yuliia Noha