

Product Configuration

WireGuard VPN module **WHMCS**

[Order now](#) | [Download](#) | [FAQ](#)

Add new product to WHMCS

System Settings->Products/Services->Create a New Product

In the **Module settings** section, select the **"PUQ WireGuard VPN"** module

DetailsPricingModule SettingsCustom FieldsConfigurable OptionsUpgradesFree DomainCross-sellsOtherLinks

Module NamePUQ WireGuard VPN

Server Groupdev.puqvpncp.com

License key

success: 2025-02-15T14:34:59+01:00

Link settings

Link to instruction

https://doc.puq.info/books/wireguarc

A link to the instruction will be reflected in the client area.

Link to VPN clients

https://doc.puq.info/books/wireguarc

A link to the VPN clients will be reflected in the client area.

☐

Disable One-time linkA One-time link to the VPN clients will be disabled in the client area.

Custom Welcome EmailDo not send email for t

Custom Change localization EmailDo not send email for t

VPN ServerDefault

Please select your server from the list. The list is loaded inconsistently from the server, you may need to log in to the panel to make changes.

VPN users settings

Bandwidth Download1000Mbit

Bandwidth Upload1000Mbit

E-mail configuration

Switch to Advanced Mode

Metric Billing

Bandwidth Usage In (GB)

Configure Pricing

ON

Bandwidth Usage Out (GB)

Configure Pricing

ON

☒ Automatically setup the product as soon as an order is placed

☐ Automatically setup the product as soon as the first payment is received

☐ Automatically setup the product when you manually accept a pending order

☐ Do not automatically setup this product

Save Changes

Cancel Changes

- **License key:** A pre-purchased license key for the **"PUQ WireGuard VPN"** module. For the module to work correctly, the key must be active

VPN Server

- Please select your server from the list. The list is loaded inconsistently from the server **PUQVPNCP**, you may need to log in to the panel to make changes.

Link settings

- **Link to instruction** - If you have prepared instructions for your customers on how to use the service, then a link to the instructions is provided here (If filled, it will be shown in the client area)
- **Link to VPN clients** - Link to download the VPN client. For example <https://www.wireguard.com/install/> (If filled, it will be shown in the client area)
- **Disable One-time link** - When this option is enabled, a one-time link to the VPN clients will be disabled in the client area, preventing the customer from using a single-use link for downloading the VPN clients.

E-mail configuration

- **Custom Welcome Email** - Drop-down list of available e-mail templates for the action of creating a new client account. Please note that it is necessary to disable the standard welcome email in order to avoid double notification
- **Custom Change localization Email** - Drop-down list of available e-mail templates for the localization change action (package change) for the client account. Please note that you need to disable the standard package change email to avoid double notification.

VPN users settings

- **Bandwidth Download** - Bandwidth Download of VPN accounts **(package change)**
- **Bandwidth Upload** - BandwidthUpload of VPN accounts **(package change)**

Metric Billing

Configure Pricing

Bandwidth Usage In (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:

☒ Per Unit ⓘ
☐ Total Volume ⓘ
☐ Graduated ⓘ

Quantity Included

0.00

Price Per GB			
PLN	EUR	UAH	USD
17.00	10.00	150.00	9.00

Close
Save

Configure Pricing

Bandwidth Usage Out (GB)

Metric Type: Monthly

Metric Unit: Gigabytes

Pricing

Scheme:

☒ Per Unit ⓘ
☐ Total Volume ⓘ
☐ Graduated ⓘ

Quantity Included

0.00

Price Per GB			
PLN	EUR	UAH	USD
18.00	10.00	150.00	9.00

Close
Save

- Bandwidth Usage In (GB):**
 - Metric Type:** Monthly
 - Metric Unit:** Gigabytes (GB)
 - Pricing Scheme:**
 - Per Unit:** Billing for each gigabyte of traffic.
 - Total Volume:** Billing for the total volume of traffic.
 - Graduated:** Billing on a graduated scale.
 - Quantity Included:** Allows you to set how many gigabytes are included in the plan.
 - Price Per GB:** Allows you to specify the cost per gigabyte of traffic in various currencies.
- Bandwidth Usage Out (GB):**

- **Metric Type:** Monthly
- **Metric Unit:** Gigabytes (GB)
- **Pricing Scheme:**
 - **Per Unit:** Billing for each gigabyte of traffic.
 - **Total Volume:** Billing for the total volume of traffic.
 - **Graduated:** Billing on a graduated scale.
- **Quantity Included:** Allows you to set how many gigabytes are included in the plan.
- **Price Per GB:** Allows you to specify the cost per gigabyte of traffic in various currencies.

Overages Billing

Overages Billing		<input checked="" type="checkbox"/> Check to Enable	
Soft Limits	Disk Usage	<input type="text" value="0"/>	<div>MB</div> <div>Bandwidth</div> <div><input type="text" value="1"/></div> <div>GB</div>
Overage Costs	Disk Usage	<input type="text" value="0.0000"/>	<div>Bandwidth</div> <div><input type="text" value="10.0000"/></div> <div>(Price Per Unit Over Above)</div>

- **Check to Enable:** Enables overage billing.
- **Soft Limits:**
 - **Disk Usage:** not use.
 - **Bandwidth:** Sets a soft limit for bandwidth usage (units: MB, GB, TB). For example, you can set a soft limit of 1 GB for bandwidth.
- **Overage Costs:**
 - **Disk Usage:** not use.
 - **Bandwidth:** Specifies the cost per unit over the soft limit for bandwidth usage.
 - **Price Per Unit Over Above:** Sets the pricing for overage units.

Revision #16

Created 25 November 2022 10:30:10 by Ruslan

Updated 22 June 2024 10:21:46 by Dmytro Kravchenko