



Add server (PUQVPNCP) in WISECP

WireGuard VPN module **WISECP**

[Order now](#) | [Download](#) | [FAQ](#)

1. Log in to the administrative area of your **WISECP**.
2. Go to module configuration.

Services -> Service Management -> Module Settings -> Other -> All Modules -> PUQ WireGuard VPN



Other

Other

Search Within Modules

Write something...



-
-
- PUQ WireGuard VPN
-

3. In the opened page, click the '**Add Server**' button.

Other

Dashboard / Module Settin

PUQ WireGuard VPN



License key

58T11Z- -1J1ASA

2023-12-18T10:38:13+01:00

Check and Save

Version: 1.0.1

Web Site

Documentation

Changelog

+ Add New Server

Server Groups

Servers PUQVPNCP

10

Show Record

Search

#	Name	Status	Group	Default	IP/Domain	Usage Stats	
23	dev.softkeel.com - B	active	Default	✔	dev.softkeel.com	3/12	
24	dev.softkeel.com - A	active	Default	⊘	466	0/44	

Showing records from 2 to 1 - 2

Prev 1 Next

4. On the opened page, enter all the necessary information:

- **Name:** Displayed name of the server.
- **Maximum Number of Accounts:** The number of services that can be on this server.
- **Server Group:** Optionally, choose the server group.
- **IP Address or Domain:** The address of the PUQVPNC server you are connecting to.
- **Access Hash:** API key that you created in the previous step on the PUQVPNC server.
- Check the **SSL** box if you want to use SSL-encrypted connection. If necessary, specify the port and perform a connection test.

Initial Settings

All Modules

PUQ WireGuard VPN

Go to Back

Add New Server

Name

dev.softkeel.com

Maximum Number of Accounts

100

Server Group

Default

Default

☐ Set as default server in group

IP Address or Domain

dev.softkeel.com

✓ Connection test Successful

Access Hash

SSL

☒ Connect using SSL

Port

443 ☐ Change standard port

Test Connection

Test Connection

Add New Server

Revision #11

Created 20 November 2023 12:33:16 by Ruslan

Updated 20 November 2023 18:01:03 by Ruslan