

4. Create new server for Proxmox in WHMCS

ProxmoxKVM module **WHMCS**

[Order now](#) | [Download](#) | [FAQ](#)

Preface

For the module to work properly, you must configure the server settings in Your main WHMCS panel. This is the place to set up a proxmox server or proxmox cluster, which will then be used to build KVM machines. Here we define the access data IP ranges and additional settings.

Attention.

If you have one server, or you do not use server groups. You need to make this server the default. By clicking on it with the mouse.

Make this server the active default for new signups

Server creation

Login to Your WHMCS panel and create new server Proxmox in WHMCS (*System Settings->Products/Services->Servers*)

System Settings->Servers->Add New Server

[Products/Services](#)

• Enter the correct **Name** and **Hostname**

• In the assigned IP Addresses you must enter a list of IP addresses of virtual machines that will be reserved for this server.

[Product Bundles](#)

[Domain Pricing](#)

[Domain Registrars](#)

Starting with version 1.3, the module started supporting IPv4/IPv6 pools.

In order to manage pools of IPv4 and IPv6 IP addresses, you need to install the PUQ Customization addon module (free)

<https://doc.puq.info/books/puq-customization-whmcs-addon/page/ip-pools>

<https://doc.puq.info/books/puq-customization-whmcs-addon/chapter/module-puqproxmoxkvm>

<https://doc.puq.info/books/puq-customization-whmcs-addon>

<https://download.puqcloud.com/WHMCS/addons/PUQ-Customization/>

Format to follow in the Assigned IP Addresses field.

To define the available pool of IP addresses, for each available IP number you should enter another line where the data is separated by the "|" separator. Each line with an IP number definition has the following structure:

<bridge>|<vlan_tag>|<IP_address>|<net_mask>|<Gateway>|<DNS1>,<DNS2>

<bridge> - the bridge to which the machine is connected is virtual.

<vlan_tag> - vlan which will be installed on the map of the network machine. In case of not using vlan, you need to set 0

Example:

```
vmbr0| 10| 192. 168. 10. 2| 24| 192. 168. 10. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr0| 10| 192. 168. 10. 3| 24| 192. 168. 10. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr0| 10| 192. 168. 10. 4| 24| 192. 168. 10. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr0| 30| 192. 168. 20. 2| 24| 192. 168. 20. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr0| 30| 192. 168. 20. 3| 24| 192. 168. 20. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr0| 30| 192. 168. 20. 4| 24| 192. 168. 20. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr1| 333| 172. 16. 5. 2| 24| 172. 16. 5. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr1| 333| 172. 16. 5. 3| 24| 172. 16. 5. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr1| 333| 172. 16. 5. 4| 24| 172. 16. 5. 1| 8. 8. 8. 8, 1. 1. 1. 1
vmbr3| 0| 10. 0. 25. 2| 24| 10. 0. 25. 1| 10. 0. 10. 10, 10. 0. 10. 20
vmbr3| 0| 10. 0. 25. 3| 24| 10. 0. 25. 1| 10. 0. 10. 10, 10. 0. 10. 20
vmbr3| 0| 10. 0. 25. 4| 24| 10. 0. 25. 1| 10. 0. 10. 10, 10. 0. 10. 20
vmbr3| 0| 10. 0. 25. 5| 24| 10. 0. 25. 1| 10. 0. 10. 10, 10. 0. 10. 20
vmbr3| 0| 10. 0. 25. 6| 24| 10. 0. 25. 1| 10. 0. 10. 10, 10. 0. 10. 20
```

Servers

Edit Server

Name	<input type="text" value="proxmox-test.uuq.pl"/>
Hostname	<input type="text" value="proxmox-test.uuq.pl"/>
IP Address	<input type="text" value="192.168.12.85"/>
Assigned IP Addresses (One per line)	<div><div>vmbr0 10 192.168.10.2 24 192.168.10.1 8.8.8.8,1.1.1.1</div><div>vmbr0 10 192.168.10.3 24 192.168.10.1 8.8.8.8,1.1.1.1</div><div>vmbr0 10 192.168.10.4 24 192.168.10.1 8.8.8.8,1.1.1.1</div><div>vmbr0 30 192.168.20.2 24 192.168.20.1 8.8.8.8,1.1.1.1</div><div>vmbr0 30 192.168.20.3 24 192.168.20.1 8.8.8.8,1.1.1.1</div><div>vmbr0 30 192.168.20.4 24 192.168.20.1 8.8.8.8,1.1.1.1</div><div>vmbr1 333 172.16.5.2 24 172.16.5.1 8.8.8.8,1.1.1.1</div><div>vmbr1 333 172.16.5.3 24 172.16.5.1 8.8.8.8,1.1.1.1</div><div>vmbr1 333 172.16.5.4 24 172.16.5.1 8.8.8.8,1.1.1.1</div><div>vmbr3 0 10.0.25.2 24 10.0.25.1 10.0.10.10,10.0.10.20</div><div>vmbr3 0 10.0.25.3 24 10.0.25.1 10.0.10.10,10.0.10.20</div><div>vmbr3 0 10.0.25.4 24 10.0.25.1 10.0.10.10,10.0.10.20</div><div>vmbr3 0 10.0.25.5 24 10.0.25.1 10.0.10.10,10.0.10.20</div><div>vmbr3 0 10.0.25.6 24 10.0.25.1 10.0.10.10,10.0.10.20</div></div>

Enter the correct data in the username and password field

- In the **Server Details** section, select the "**PUQ Proxmox KVM**" module and enter the correct **username** and **password** for the **Proxmox web interface**.
- To check, click the "**Test connection**" button

Note that the username is entered with the Proxmox account type (@pam or @pve)

During operation, the module will automatically fill in the Access Hash field. This field does not need to be completed.

Server Details

Module	PUQ Proxmox KVM Test Connection
	✓ Connection successful. Some values have been auto-filled.
Username	root@pam
Password	*****
Access Hash	PVE:root@pam:631738FC::drXAr+4i1VbSnydqEa6zzj+cs6WQivErMvD/ijlNR9N/qat6afwgiKzpe8HSITUHyGhE9h7YcMJu78eScDG+t9NCY81OfF0XMe1TEUGUs1oBNCnODRYv3zgXLKPsK/FtF/cXAUCLRkT/Vu9o1CPIIY7Cr4CSgtjaeDaU7R8bxDn917hdmpZU1NfCjIRWDp/vR67ug9PZIMR0+cB53KvzJBp3p3V3ujkC8NLnBpbN9ADfsTAFUKAPtYMqHYLHOZr4VaykDI0vlgYeywYOJovZkf+wtGU3GsaLnnDjCP1hpa9goV8PjO86u7TKMMVYqJ9xRzlf9YpQBcjzIHNO3Czpg== 631738FC:Wp260ln4k/hLTuFtQ8SrrNjAzGw2qKE0/jwlej2iGY
Secure	<input checked="" type="checkbox"/> Check to use SSL Mode for Connections
Port	8006 <input type="checkbox"/> Override with Custom Port

Attention

If you have one server, or you do not use server groups. You need to make this server the default. By clicking on it with the mouse.

Make this server the active default for new signups

PUQ Proxmox KVM			
proxmox-test.uug.pl *		5/200 (3%)	Not Available Login to Proxmox
	Make this server the active default for new signups		

