

# Linux IKEv2 client configuration

[Order now](#) | [Download](#) | [FAQ](#)

In order to connect to a VPN, follow these steps:

1. Open the link you received in a browser to get instructions and configuration for your new VPN connection. And you will see the following page in the browser window

2. In order to start the configuration you need install some software, before installing the software, do the following to update the package list using the command `sudo apt update`. After the package list is updated, install additional software:

```
|sudo apt install strongswan libcharon-extra-plugins|
```

3. Next, prepare a certificate to encrypt the connection. You can download the certificate, open the certificate file as text and create a new file at `|nano /etc/ipsec.d/cacerts/ca-cert.pem|`

4. To prevent automatic connection, use `systemctl` to disable StrongSwan from starting automatically

```
|sudo systemctl disable --now strongswan-starter|
```

5. Next, you need to edit or create a file with authentication data

```
|sudo nano /etc/ipsec.secrets|
```

In this file, you need to enter your login and password data from the IKEv2 section

```
your_username : EAP "your_password"
```

6. The next step is to edit the configuration file

```
|nano /etc/ipsec.conf|
```

The contents of the configuration file should be the following

## config setup

```
conn ikev2-rw
    right=adres_server
    # This should match the `leftid` value on your server's configuration
    rightid=adres_server
    rightsubnet=0.0.0.0/0
    rightauth=pubkey
    leftsourceip=%cfg
    leftauth=eap-mschapv2
    leftid=your_username
    eap_identity=%identity
    auto=start
```

**Attention!** Please note that you need to enter your data in the configuration file and the authentication file.

7. To activate the connection, enter the command `sudo ipsec start` and to disable run the command `sudo ipsec stop`

---

Revision #8

Created 13 December 2022 10:17:51 by Ruslan

Updated 16 October 2023 09:04:20 by Yuliia Noha